

# Protel D X P 2004之破解

主题:

Protel D X P 2004之破解





图 2



## Protel D X P 2004之破解

ProtelEvaluationLicenseEY67-2SAG.alf

iJBdhVfQrNfQRHuyHFFjAmH8ide3vFESaiVhbrBufncXORAMh0jkcPsP+Qi3oGwcdDKTMYPKGzWuIAtUleEq+CUqreOkRMKwaIq4Puq0

把名字变成ProtelEvaluationLicenseEY67-2SAG.alf

ProtelEvaluationLicenseEY67-2SAG下载:

下载后把“.pdf”扩展名去掉成为RAR文件

<http://www.2licsearch.com/buzi/upimage/upfile/2004461343350.pdf>

上面的哪个用右键别存为!

Protel D X P 2004之破解文件

Protel D X P 2004之破解文件

安装Protel D X P 2004后把它放到软件安装根目录进行破解

下载后把“.pdf”扩展名去掉成为RAR文件

<http://www.2licsearch.com/buzi/upimage/upfile/2004461347570.pdf>

Protel D X P 2004试用版可以去申请光盘

[http://www.altium.cn/protel/trial\\_dl/form\\_trial\\_rego.asp](http://www.altium.cn/protel/trial_dl/form_trial_rego.asp)

Protel D X P 2004试用版可以去申请光盘

[http://www.altium.cn/protel/trial\\_dl/form\\_trial\\_rego.asp](http://www.altium.cn/protel/trial_dl/form_trial_rego.asp)

## Protel D X P 2004之破解

从<http://www.avrw.com/BBS/>里面dd2033老兄的破解方法

Protel2004破解方法!!!

首先用ollydbg或W32Dasm进行反编译,然后跳到下面程序段

```
00682D14 |. 68 AB2D6800   PUSH DXP.00682DAB
00682D19 |. 64:FF30       PUSH DWORD PTR FS:[EAX]
00682D1C |. 64:8920       MOV DWORD PTR FS:[EAX],ESP
00682D1F |. 8B45 FC       MOV EAX,DWORD PTR SS:[EBP-4]
00682D22 |. E8 B1B2F0FF   CALL DXP.0058DFD8
00682D27 |. 85C0          TEST EAX,EAX           // 验证License是否有效
00682D29 |. 75 0F         JNZ SHORT DXP.00682D3A // 有效就跳转
00682D2B |. 8B45 F8       MOV EAX,DWORD PTR SS:[EBP-8]
00682D2E |. BA C02D6800   MOV EDX,DXP.00682DC0   ; ASCII
"Unlicensed"
00682D33 |. E8 402BD8FF   CALL DXP.00405878     // 无效进入
00682D38 |. EB 5B         JMP SHORT DXP.00682D95
00682D3A |> 33D2         XOR EDX,EDX
00682D3C |. 8B45 FC       MOV EAX,DWORD PTR SS:[EBP-4]
00682D3F |. E8 B0B2F0FF   CALL DXP.0058DFF4
00682D44 |. 8945 F4       MOV DWORD PTR SS:[EBP-C],EAX
00682D47 |. 8B45 F8       MOV EAX,DWORD PTR SS:[EBP-8]
00682D4A |. 8B55 F4       MOV EDX,DWORD PTR SS:[EBP-C]
00682D4D |. 8B4A 04       MOV ECX,DWORD PTR DS:[EDX+4]
00682D50 |. BA D42D6800   MOV EDX,DXP.00682DD4   ; ASCII "Licensed to "
00682D55 |. E8 DE2DD8FF   CALL DXP.00405B38
00682D5A |. 8B45 F4       MOV EAX,DWORD PTR SS:[EBP-C]
00682D5D |. 8378 08 01    CMP DWORD PTR DS:[EAX+8],1
00682D61 |. 75 32         JNZ SHORT DXP.00682D95
00682D63 |. 8B45 F8       MOV EAX,DWORD PTR SS:[EBP-8]
00682D66 |. FF30         PUSH DWORD PTR DS:[EAX]
00682D68 |. 68 EC2D6800   PUSH DXP.00682DEC
00682D6D |. 8B45 F4       MOV EAX,DWORD PTR SS:[EBP-C]
00682D70 |. E8 ABA8F0FF   CALL DXP.0058D620
00682D75 |. 8BD0         MOV EDX,EAX
00682D77 |. 8D4D F0       LEA ECX,DWORD PTR SS:[EBP-10]
00682D7A |. 8B45 F4       MOV EAX,DWORD PTR SS:[EBP-C]
00682D7D |. 8B40 2C       MOV EAX,DWORD PTR DS:[EAX+2C]
00682D80 |. E8 5B71FFFF   CALL DXP.00679EE0
00682D85 |. FF75 F0       PUSH DWORD PTR SS:[EBP-10]
00682D88 |. 8B45 F8       MOV EAX,DWORD PTR SS:[EBP-8]
00682D8B |. BA 03000000   MOV EDX,3
00682D90 |. E8 172ED8FF   CALL DXP.00405BAC
00682D95 |> 33C0         XOR EAX,EAX
00682D97 |. 5A          POP EDX
00682D98 |. 59          POP ECX
```

## Protel DXP 2004之破解

```
00682D99 |. 59          POP ECX
00682D9A |. 64:8910      MOV DWORD PTR FS:[EAX], EDX
00682D9D |. 68 B22D6800  PUSH DXP.00682DB2
00682DA2 |> 8D45 F0      LEA EAX, DWORD PTR SS:[EBP-10]
00682DA5 |. E8 7A2AD8FF  CALL DXP.00405824
00682DAA \. C3          RETN
```

具体修改方法如下:

将     00682D29     75 0F            JNZ SHORT DXP.00682D3A

改为   00682D29     74 0F            JZ  SHORT DXP.00682D3A

或者   00682D29     EB 0F            JMP SHORT DXP.00682D3A

即可保存后运行就搞定了!!!